


export 101



import 107

Fig. 1 PRIOR ART




Fig. 2 PRIOR ART




Fig. 3




Fig. 4




Fig. 5




Fig. 6



725




Fig. 7

EXPORT 701




Fig. 8

IMPORT from dump file set 801




Fig. 9

| Column Name | Datatype | Meaning |
|-------------------|---------------|---|
| PROCESS ORDER | NUMBER | If <0, corresponding row describes an object processed by the job. The value of PROCESS_ORDER reflects the order in which the corresponding object must be imported in relation to other objects. If <0, corresponding row describes an attribute of the job. The value of PROCESS_ORDER identifies which job attribute is being defined. -71 is reserved as a pseudo OBJECT row to reference the Master Table at Export time. -72 is reserved as a pseudo OBJECT row to reference the Master Table in Import/SQL file operations. |
| DUPLICATE | NUMBER | When multiple rows are needed to represent an object, DUPLICATE is used to define the order for them. The first row will have DUPLICATE set to 0 and succeeding rows will use 1 and up. If only a single row is used to identify an object, DUPLICATE will be set to 0. Multiple rows are used to identify all of the pieces belonging to a partition. |
| DUMP FILEID | NUMBER | The identification of the data representing this object in the dump set. Duplicate rows for the TABLE_DATA object row will specify the additional file pieces used for a table/partition. The identification requires four pieces of information: The numeric id used to represent the file in the dump file set. The block position of the data within the file. The length of the data in bytes. The total number of blocks allocated for the object. |
| DUMP_POSITION | NUMBER | |
| DUMP_LENGTH | NUMBER | |
| DUMP_ALLOCATION | NUMBER | |
| COMPLETED_ROWS | NUMBER | The number of rows that have been moved in the current file piece. (Used by GET STATUS) |
| ERROR_COUNT | NUMBER | The number of errors detected in the current file piece. (Used by GET STATUS) |
| ELAPSED_TIME | NUMBER | Amount of time spent processing the piece in 100ths of seconds. (Used by GET STATUS) |
| OBJECT_TYPE_PATH | VARCHAR(200) | Metadata API pathname for object as defined in the DATABASE_EXPORT OBJECTS view. |
| OBJECT_PATH_SEQNO | NUMBER | Sequence number for object type. This field orders object types for import. |
| OBJECT_TYPE | VARCHAR(230) | Simple object type name for object (without path info) |
| OBJECT_NAME | VARCHAR(2500) | Name of the object in the dump file set. For synonyms and Java objects this may be the short name for the object. |
| LONG_OBJECT_NAME | VARCHAR(4000) | Name of the object in the dump file set. |
| OBJECT_SCHEMA | VARCHAR(230) | Schema owning the referenced object. NULL, if object is not a schema object. For import, this schema may be changed due to schema renaming. |
| ORIGINAL_OBJECT | VARCHAR(230) | Schema owning the referenced object prior to any schema rename. NULL, if object is not a schema object. |
| FLAGS | NUMBER | X00000001 Unused X00000002 has nested tables (valid only for TABLE objects) X00000004 table is being repartitioned on import and partition cannot be loaded in parallel (valid only for TABLE objects). X00000008 Unused X00000010 table uses row-level security. X00000020 table is a table used in a domain index X00000040 object is partitioned X00000080 table is a used as a nested table. |
| 503 | | |
| 504 | | |
| 509 | | |
| 1001 | | |
| 1003 | | |
| 513 | | |
| 1005 | | |
| 511 | | |
| object row 507A | | |

| | | | | | |
|-----------------|------|-------------------|--------------|---|--|
| 513 | 1101 | COMPLETION TIME | DATE | /Import (only) Timestamp entered when Import attempt to define the object. This timestamp may be used on restart to determine whether Import defined the object or whether the object was preexisting in the database before Import ran. | |
| | | OBJECT TABLESPACE | VARCHAR2(30) | Tablespace used to store the object if the object requires storage. | |
| 511 | 1103 | SIZE ESTIMATE | NUMBER | Estimated size of TABLE DATA object in bytes. During Import, DUMP LENGTH is a more accurate measure of size. | |
| | | OBJECT ROW | NUMBER | Index into the XML document for the current object. This field is used when multiple objects are defined in a single XML document. This column is not used for TABLE DATA objects. | |
| 513 | 1103 | IN PROGRESS | CHAR(1) | (Used in Import and Network only) If "Y", indicates that the creation of the current object was partially defined and may require special cleanup on restart. | |
| | | PARTITION NAME | VARCHAR2(30) | For TABLE DATA objects, identifies the (sub)partition that contains the set of rows. Set to NULL, otherwise. | |
| 511 | | PROCESSING_STATE | CHAR(1) | If -> Object definition has not been retrieved from source database. R -> Object definition has been completely retrieved from source database. For Export, object has also been written to dump file set. U -> Object has been read from source database, but its state is unknown (i.e., "in progress") in the target database. | |
| | | PROCESSING_STATUS | CHAR(1) | W -> Object has been written to the target database. + -> Intermediate state used when filtering an export master table for an Import job. - -> Intermediate state used when filtering an export master table for an Import job. | |
| 513 | | PARALLELIZATION | NUMBER | For TABLE DATA objects, specifies the maximum parallelization recommended for the partition in the data layer. It may be decreased by the scheduler in the MCP during assignment to a worker or Import if the parallelization cannot be supported by the job. | |
| | | UNLOAD METHOD | NUMBER | For TABLE DATA objects, specifies unload method. 1 -> Direct Path or Network 2 -> External Table 4 -> Either method is acceptable -1 -> Neither method is acceptable | |
| 511 | 1107 | GRANULARITY | NUMBER | Number of data granules within a file piece. A granule is unit of allocation inside of external table processing. | |
| | | SCN | NUMBER | Identifies the consistent SCN for TABLE and TABLE DATA objects when TABLE CONSISTENCY is set or FLASHBACK is set or safe scn is set. | |
| object row 507B | 1111 | | | | |

Fig. 11

| | | | | | |
|-----|-----------------|------|--------------|--------------|---|
| 511 | object row 507C | 1201 | DOMAIN INDEX | VARCHAR(230) | If object is a secondary object, identifies the domain index that created the object, NULL otherwise. |
| | | | DOMAIN INDEX | VARCHAR(230) | |
| | | | GRANTOR | VARCHAR(230) | For grants, the schema that originally created the grant. |
| | | | XML, CLOB | CLOB | For Table objects, the XML representation of the metadata to recreate the object. Also used to load data for Table data objects within the table. |

| | | | | | |
|------|-----------------------|--------|------------------|----------------|---|
| 1207 | 503 | 504 | Column Name | Datatype | Meaning |
| | | | PROCESS_ORDER | NUMBER | -1 for Export jobs, -2 for Import and SQL_*File jobs. |
| | | | DUPLICATE | NUMBER | 0 |
| | | | OBJECT_NAME | VARCHAR(2500) | Name of the job (should be the same as the table name) |
| | | | OBJECT_LONG_NAME | VARCHAR(4000) | Name of the job (should be the same as the table name) |
| | | | USER_NAME | VARCHAR(230) | Username who initiated operation. (This should be same name as the owner of the Master Table.) |
| | | | OPERATION | VARCHAR(230) | One of the following values: EXPORT, IMPORT, SQL_*FILE |
| | | | JOB_MODE | VARCHAR(230) | One of the following values: FULL, SCHEMA, TABLE, TABLESPACE, TRANSPORTABLE |
| | | | REMOTE_LINK | VARCHAR(24000) | Network link used for job (Null if none). |
| | | | VERSION | NUMBER | Version control for Master Table format. |
| | | | DB_VERSION | VARCHAR(230) | The version of the database object for this operation. |
| | | | STATE | VARCHAR(230) | One of the following values: DEFINING, EXECUTING, IDLING, STOPPING, STOPPED, WAITING, COMPLETING, COMPLETED. |
| | | | PHASE | NUMBER | The sequence position in the tasks to accomplish the job. The meaning of each number is dependent upon the operation being performed. |
| | | | GUID | RAW(16) | Uniquely unique identifier for describing the job. The GUID is used to label files as belonging to the job. |
| 1215 | START_TIME | DATE | DATE | NUMBER | Datetime when the job was OPENED. |
| | | | | | |
| | | | | | |
| | | | | | |
| 1217 | BLOCK_SIZE | NUMBER | NUMBER | NUMBER | ksq block size used in job. This is also defined in the header of each dump file. |
| | | | | | |
| | | | | | |
| | | | | | |
| 1219 | META_DATA_BUFFER_SIZE | NUMBER | NUMBER | NUMBER | number of blocks in a ksq buffer for processing metadata |
| | | | | | |
| | | | | | |
| | | | | | |
| 1217 | DATA_BUFFER_SIZE | NUMBER | NUMBER | NUMBER | number of blocks in a ksq buffer for processing data |
| | | | | | |
| | | | | | |
| | | | | | |
| 1219 | DEGREE | NUMBER | NUMBER | NUMBER | Number of worker processes that can be active at any time |
| | | | | | |
| | | | | | |
| | | | | | |
| 1219 | ERROR_COUNT | NUMBER | NUMBER | NUMBER | Number of errors reported for job |
| | | | | | |
| | | | | | |
| | | | | | |

job state row 1205A (517)

Fig. 12

1301

| | | |
|------------------|----------------|---|
| TOTAL_BYTES | NUMBER | For Export, estimated size of data in job. For Import, size of data in job to be loaded. |
| PLATFORM | VARCHAR2(100) | Platform used for the Export/Import |
| INSTANCE | VARCHAR2(15) | Instance name that job is running upon (RAC only) |
| ABORT_STEP | NUMBER | Process_order number of Object row that will cause the job to abort. For testing purposes only. |
| SCN | NUMBER | The System Change Number passed to Logical Standby for all DDL creations. This is *not* the SCN used for TABLE DATA OBJECT rows; they each have their own. |
| OBJECT_TYPE_PATH | VARCHAR2(200) | Final termination message for job |
| OLD_VALUE | VARCHAR2(4000) | This is the opaque "cookie" returned to us by dbms_internal safe_scn.get_scn during export and handed in during import & network. Used by Logical Standby / Streams |
| FLAGS | NUMBER | X00000001 Job is interesting for either streams or logical standby and the SCNs for tables need to be supplied via the safe_scn package. |

job state row 1205B (517)

| Column Name | Datatype | Meaning |
|---------------|----------|---|
| PROCESS_ORDER | NUMBER | -3 for Export jobs. |
| DUPLICATE | NUMBER | 0 |
| SEED | NUMBER | Highest value of PROCESS_ORDER in Master Table. Originally set to 1 when Master Table is initially created. |

MAX_PROCESS_ORDER row 1303 (517)

504

1307

| Column Name | Datatype | Meaning |
|-------------------|---------------|---|
| PROCESS_ORDER | NUMBER | -5 for Export jobs. -6 for Import and SQL File jobs. |
| DUPLICATE | NUMBER | The sequence number for each object type |
| OBJECT_TYPE_PATH | VARCHAR2(200) | Path of object type whose processing has completed. |
| OBJECT_PATH_SEQNO | NUMBER | Sequence number for object type. This field orders object types for import. |
| COMPLETION_TIME | DATE | Time when processing of object was completed. |
| COMPLETED_ROWS | NUMBER | The number of objects of current object path have been processed. |

TYPE_COMPLETION row 1305
(517)

Fig. 13

| | Column Name | Datatype | Meaning |
|------|----------------|----------------|---|
| 503 | PROCESS_ORDER | NUMBER | -21 for Export jobs. -22 for Import and SQL File jobs. |
| 504 | DUPLICATE | NUMBER | Internal number assigned to each file as it is specified in export time. File references by OBJECT rows always use this number rather than the file name. |
| 1403 | FILE_TYPE | NUMBER | 0 if disk file. |
| 1405 | USER_DIRECTORY | VARCHAR2(4000) | Directory path used for dumpfile. |
| | USER_FILE_NAME | VARCHAR2(4000) | Original file name specified by user |
| | FILE_NAME | VARCHAR2(4000) | Fully resolved name (including path information) for file. |
| | FILE_MAX_SIZE | NUMBER | Maximum size for the file. 0 if file is extendable. |

FILE row 1401 (521)

| | Column Name | Datatype | Meaning |
|------|---------------|----------------|--|
| 503 | PROCESS_ORDER | NUMBER | -23 for Export jobs. -24 for Import and SQL File jobs. |
| 504 | DUPLICATE | NUMBER | Ordinal position for when this ADD_FILE was specified (used to maintain round robin ordering between wildcarded names). |
| 1411 | FILE_NAME | VARCHAR2(4000) | Template for filename including substitution variables. |
| 1413 | FILE_MAX_SIZE | NUMBER | Maximum size for the file. 0 if file is extendable. |
| 1415 | SEED | NUMBER | Last value used for resolving substitution variables. Each wildcard specification needs a unique number since ADD_FILES can come in after the job has started. |
| 1417 | LAST_FILE | NUMBER | File number of last file resolved from this wildcard string. This column is used to identify where we are in the round robin expansion of wildcarded names. |

WILDCARD_FILE row 1409 (521)

Fig. 14

| | Column Name | Datatype | Meaning |
|------|------------------|----------------|--|
| 503 | PROCESS_ORDER | NUMBER | -41 for Export jobs. -42 for Import and SQL_File jobs. |
| 504 | DUPLICATE | NUMBER | Internal id for the worker process. |
| 1503 | PROCESS_NAME | VARCHAR2(30) | Process name for the worker process |
| 1505 | OBJECT_NUMBER | NUMBER | PROCESS_ORDER value for the object being processed by the worker process. |
| | OBJECT_SCHEMA | VARCHAR2(30) | The schema of the object being processed. Null if not in EXECUTING state or processing a non-schema object. |
| | OBJECT_NAME | VARCHAR2(500) | The name of the object being processed. Null if not in EXECUTING state or processing an unnamed object. |
| | OBJECT_LONG_NAME | VARCHAR2(4000) | The name of the object being processed. Null if not in EXECUTING state or processing an unnamed object. |
| | OBJECT_TYPE_PATH | VARCHAR2(200) | The object type pathname of the object being processed. Null if not in EXECUTING state. |
| 1507 | PARTITION_NAME | VARCHAR2(30) | The name of the partition of the object being processed. Only object within a partitioned table. Null otherwise. |
| | TOTAL_BYTES | NUMBER | Number of bytes within a TABLE DATA object. On EXPORT, number may be a estimate. NULL if no estimate is available on object or if work is not processing a TABLE DATA object. |
| | COMPLETED_ROWS | NUMBER | Number of data rows written or read for current TABLE DATA object. For other objects, the number of objects of current object path have been processed. |
| | LAST_UPDATE | DATE | Time of last update for Worker row. Used to approximate the time of a crash during restart. |
| | WORK_ITEM | VARCHAR2(30) | Current work item being processed by Worker. NULL, if worker is idle. Possible values are UNLOAD METADATA, UNLOAD DATA, LOAD METADATA, LOAD DATA, ESTIMATE JOB, SQL FILE JOB, RELEASE FILES, and EXITING |
| 1509 | STATE | VARCHAR2(30) | One of the following values: WORK, WAITING, FILE_WAITING, EXECUTING, MASTER. WORK_WAITING -- worker is waiting for work from the Master Control Process. FILE_WAITING -- worker is waiting for a file space from the Master Control Process. EXECUTING -- worker is processing one or more objects. See OBJECT_NUMBER and OBJECT_ROWID columns for details. MASTER -- Worker Process is either saving or restoring the Master Table to/from the dump file set. |
| | METADATA_IO | NUMBER | Amount of Metadata written to the dump file (for export) or read from the dump file (for Import) or transferred over the link since last restart for this Worker. |
| | DATA_IO | NUMBER | Amount of table data written to the dump file (for Export) or read from the dump file (for Import) or transferred over the link since last restart for this Worker. |
| | CUMULATIVE_TIME | NUMBER | The amount of time that this worker process has spent actively processing the job. |

WORKER row 1501 (517)

Fig. 15

| | Column Name | Datatype | Meaning |
|------|-----------------|----------|--|
| 503 | PROCESS_ORDER | NUMBER | -7 for Export jobs. -8 for Import and SQL_*File jobs. |
| 504 | DUPLICATE | NUMBER | 0 |
| 1603 | METADATA_IO | NUMBER | Amount of Metadata written to the dump file (for export) or read from the dump file (for Import) or transferred over the link (for Import over a network). |
| | DATA_IO | NUMBER | Amount of table data written to the dump file (for Export) or read from the dump file (for Import) or transferred over the link (for Import over a network). |
| | TOTAL_BYTES | NUMBER | An estimate of the total size of the job. For Import from files, the total size of the requested data within the dump file. |
| | CUMULATIVE_TIME | NUMBER | Sum of the amount of time that each worker process has spent actively processing the job in hundredths of a second. If 3 workers were active for an hour, this column would contain 1080000. |

RESTART_STATUS row 1601 (517)

| | Column Name | Datatype | Meaning |
|------|------------------|---------------|---|
| 503 | PROCESS_ORDER | NUMBER | -9 for Export jobs. -10 for Import jobs. |
| 504 | DUPLICATE | NUMBER | Unique key assigned to each (re)start of the job. The first start of a job will be represented by DUPLICATE 0. |
| 1605 | METADATA_IO | NUMBER | Bytes of Metadata written to the dump file (for export) or read from the dump file (for Import) or transferred over the link (for Network). |
| | DATA_IO | NUMBER | Bytes of table data written to the dump file (for Export) or read from the dump file (for Import) or transferred over the link (for Network). |
| | TOTAL_BYTES | NUMBER | For Export and Network, an estimate of the total size of the Operation (if available). For Import, the total size of the requested data within the dump file. |
| | ERROR_COUNT | NUMBER | Number of errors reported for job |
| 1606 | CUMULATIVE_TIME | NUMBER | Sum of the amount of time that each worker process has spent actively processing the job. If 3 workers were active for an hour, this column would contain 1080000. Using DATA_IO, TOTAL_BYTES, CUMULATIVE_TIME, and JOB_STATE_DEGREE, an estimate of the remaining time for the job will be possible. |
| 1607 | OBJECT_TYPE_PATH | VARCHAR2(200) | Final termination message from previous job incarnation. |
| | ELAPSED_TIME | NUMBER | Amount of time that elapsed between the restart and the latest timestamp found on the next restart in 100ths of seconds |
| | START_TIME | DATE | Starting time for previous incarnation of job. |
| | PLATFORM | VARCHAR2(100) | Platform used during previous incarnation of job. |
| | INSTANCE | VARCHAR2(15) | Instance name that job incarnation ran upon (RAC only) |
| | DEGREE | NUMBER | Degree of parallelism at end of previous incarnation of job. |

RESTART row 1605 (519)

Fig. 16

| | Column Name | Datatype | Meaning |
|--------|---------------|----------------|---|
| 503 | PROCESS_ORDER | NUMBER | -51 for Export jobs. -52 for Import and SQL_File jobs. |
| 504 | DUPLICATE | NUMBER | Internal Id for distinguishing Data Filters |
| 1703 { | NAME | VARCHAR2(30) | Name of filter. |
| 1705 | VALUE_T | VARCHAR2(4000) | Definition of a text filter. |
| 1707 | VALUE_N | NUMBER | Definition of a numerical filter. |
| | OBJECT_SCHEMA | VARCHAR2(30) | Schema of table to which filter applies |
| | OBJECT_NAME | VARCHAR2(30) | Table for which filter applies |

DATA_FILTER row 1701 (523)

| | Column Name | Datatype | Meaning |
|--------|------------------|----------------|--|
| 503 | PROCESS_ORDER | NUMBER | -53 for Export jobs. -54 for Import and SQL_File jobs. |
| 504 | DUPLICATE | NUMBER | Internal Id for distinguishing Metadata Filters |
| 1711 { | NAME | VARCHAR2(30) | Name of filter. |
| 1713 | VALUE_T | VARCHAR2(4000) | Definition of filter |
| | OBJECT_TYPE_PATH | VARCHAR2(200) | Object class affected by the filter. If NULL, the filter affects all object classes. |

METADATA_FILTER row 1709 (523)

| | Column Name | Datatype | Meaning |
|--------|---------------|----------------|---|
| 503 | PROCESS_ORDER | NUMBER | -57 for Export and Estimate jobs -58 for Import, Network and SQL_File jobs. |
| 504 | DUPLICATE | NUMBER | Internal Id for distinguishing Metadata transforms |
| 1717 { | NAME | VARCHAR2(30) | Name of Remap or Transform. Legal name is: SEGMENT, ATTRIBUTES. |
| 1719 | OLD_VALUE | VARCHAR2(4000) | Specifies value to be remapped for remaps. Null otherwise. |
| 1721 | VALUE_T | VARCHAR2(4000) | Specifies new value for remaps. For transforms, specifies the value. |
| 1723 | VALUE_N | NUMBER | Definition of a numerical filter. |
| | OBJECT_TYPE | VARCHAR2(30) | Object class affected by the remap or transform. If NULL, the remap or transform affects all applicable object classes. |

METADATA_TRANSFORM row 1715 (525)

Fig. 17

| Column Name | Datatype | Meaning |
|-------------------|----------------|--|
| 503 PROCESS_ORDER | NUMBER | -59 for Export jobs. -60 for Import and SQL_File jobs. |
| 504 DUPLICATE | NUMBER | Internal Id for distinguishing Parameters |
| NAME | VARCHAR2(30) | Name of PARAMETER. |
| IS_DEFAULT | NUMBER | If non-zero, parameter setting was not supplied by the client. |
| VALUE_T | VARCHAR2(4000) | Specifies the value set for a text parameter. |
| VALUE_N | NUMBER | Definition of a numerical parameter. |

PARAMETER row 1801 (527)

| Column Name | Datatype | Meaning |
|-------------------|----------------|--|
| 503 PROCESS_ORDER | NUMBER | -73 for Export jobs. -74 for Import and SQL_File jobs. |
| 504 DUPLICATE | NUMBER | 0 |
| 1807 VALUE_T | VARCHAR2(4000) | A DDL command to reestablish the NLS settings for the job. |

NLS_PARAMS row 1805 (527)

Fig. 18

```

DECLARE
    handle      NUMBER;

BEGIN
1903     handle := DBMS_DATAPUMP.OPEN( 'EXPORT', 'FULL', NULL,
                                         'MYDEMOVE_EXPORT');
1905     {
        DBMS_DATAPUMP.ADD_FILE(handle, 'file1.dmp',
                                   'MY_DIR1', '600M');
        DBMS_DATAPUMP.ADD_FILE(handle, 'file2.dmp',
                                   'MY_DIR2', '600M');
        DBMS_DATAPUMP.ADD_FILE(handle, 'file3.dmp',
                                   'MY_DIR3', '600M');
1907     DBMS_DATAPUMP.METADATA_FILTER(handle, 'SCHEMA_EXPR',
                                         '!= ''BLAKE''');
1909     DBMS_DATAPUMP.SET_PARALLEL(handle, 3);
1911     DBMS_DATAPUMP.START_JOB(handle);
1913     DBMS_DATAPUMP.DETACH(handle);

END;
1901

```

```

DECLARE
    handle      NUMBER;

BEGIN
1917     handle := DBMS_DATAPUMP.ATTACH ('MYDEMOVE_EXPORT');
1919     DBMS_DATAPUMP.STOP_JOB(handle, 1, 1, 0);

END;
1915

```

```

DECLARE
    handle      NUMBER;

BEGIN
1923     handle := DBMS_DATAPUMP.ATTACH ('MYDEMOVE_EXPORT');
1925     {
        DBMS_DATAPUMP.ADD_FILE(handle, 'file4.dmp',
                                   'MY_DIR4', '600M');
        DBMS_DATAPUMP.ADD_FILE(handle, 'file5.dmp',
                                   'MY_DIR5', '600M');

1927     DBMS_DATAPUMP.SET_PARALLEL(handle, 5);
1929     DBMS_DATAPUMP.START_JOB(handle);
1931     DBMS_DATAPUMP.DETACH(handle);

END;
1921

```

Fig. 19

```

BEGIN
  2003 handle := DBMS_DATAPUMP.OPEN( 'IMPORT', 'FULL', NULL,
                                     'MYDEMOVE_IMP' );

  2005 DBMS_DATAPUMP.SET_PARAMETER(handle, 'KEEP_MASTER', 0);
  2007 {
    DBMS_DATAPUMP.ADD_FILE(handle, 'file1.dmp',
                              'MY_NEWDIR1', '600M');
    DBMS_DATAPUMP.ADD_FILE(handle, 'file2.dmp',
                              'MY_NEWDIR2', '600M');
    DBMS_DATAPUMP.ADD_FILE(handle, 'file3.dmp',
                              'MY_NEWDIR3', '600M');
    DBMS_DATAPUMP.ADD_FILE(handle, 'file4.dmp',
                              'MY_NEWDIR4', '600M');
    DBMS_DATAPUMP.ADD_FILE(handle, 'file5.dmp',
                              'MY_NEWDIR5', '600M');

  2009 DBMS_DATAPUMP.METADATA_REMAP(handle, 'MAP_TABLESPACE',
                                     'USER1', 'NEWUSER1');
  2011 DBMS_DATAPUMP.SET_PARALLEL(handle, 4);
  2013 DBMS_DATAPUMP.START_JOB(handle);
  2015 DBMS_DATAPUMP.DETACH(handle);
END;

```

2001

Fig. 20

Table 1: APIs and Job states

| API | Valid Job states for API | Description |
|-------------------------|---|---|
| ADD_FILE 2103 | Defining Executing ^a Idling ^a Stop pending | Specifies a file for the dump file set, or the location of the log file or the location of the file to receive the SQL_FILE output. |
| ATTACH 2105 | Defining Executing Idling Stop pending Stopped Completing Completed | Allows a user session to monitor a job |
| DATA_FILTER 2107 | Defining | Restricts data processed by a job |
| DETACH 2109 | Defining Executing | Disconnects a user session from a job |
| GET_STATUS 2111 | Idling | Obtains the status of a job |
| LOG_ENTRY 2113 | Stop pending Completing | Adds an entry to the log file |
| METADATA_FILTER 2115 | Defining | Restricts metadata processed by a job |
| METADATA_REMAP 2117 | Defining | Remaps metadata processed by a job |
| 2119 METADATA_TRANSFORM | Defining | Alters metadata processed by a job |
| OPEN 2121 | Undefined | Creates a new job |
| SET_PARALLEL 2123 | Defining Executing Idling Stop pending | Specifies parallelism for a job |
| SET_PARAMETER 2125 | Defining | Alters default processing by a job |
| START_JOB 2127 | Defining Idling | Begins/resumes executing a job |
| STOP_JOB 2129 | Defining Executing Idling | Initiates orderly shutdown of a job |
| | Stop pending | |

a. Export jobs only

Fig. 21




Fig. 22




Fig. 23




Fig. 24